

Getting Started Guide Parallels Plesk Panel 10 for your Linux server

Getting Started Guide: Parallels Plesk Panel 10, Linux Server

Version 1.2 (9.25.2012)

© Copyright 2012. All rights reserved.

Distribution of this work or derivative of this work is prohibited unless prior written permission is obtained from the copyright holder.

Trademarks used in this book

Linux® is a registered trademark of Linus Torvalds.

Parallels Plesk Panel® is a registered trademark of Parallels, Inc.

SSH® and Secure Shell® are trademarks of SSH Communications Security, Inc.

RedHat® and Fedora® are registered trademarks of Red Hat Software, Inc.

Mac® is a registered trademark of Apple Computer, Inc.

UNIX® is a registered trademark of The Open Group.

Windows XP®, Entourage®, and Outlook® are registered trademarks of Microsoft Corporation in the United States and/or other countries.

Thunderbird™ is an unregistered trademark of the Mozilla Foundation.

All other trademarks and copyrights are the property of their respective owners.

Table of Contents

Introduction	5
SECURITY INFORMATION	5
REPROVISIONING YOUR SERVER	6
GETTING HELP	7
OTHER RESOURCES	9
Setting up Your Server	10
CHOOSING A HOST NAME, USER NAME, AND PASSWORD	10
LOGGING IN TO YOUR MANAGER FOR THE FIRST TIME	14
Connecting to Your Server	15
CONNECTING TO YOUR SERVER USING PLESK	16
CONNECTING TO YOUR SERVER USING SSH	19
GAINING ROOT ACCESS ON YOUR SERVER	21

Adding Domain Names to Your Server	23
LOGGING IN TO PLESK	24
Setting up DNS for Your Domains	31
ACCESSING YOUR DOMAIN USING FTP (UPLOADING FILES)	41
Setting up Email on Your Server	42
USING PARALLELS PLESK PANEL TO SET UP AN EMAIL ACCOUNT	42
ACCESSING YOUR ACCOUNT WITH AN EMAIL CLIENT	45
USING WEBMAIL TO ACCESS YOUR EMAIL	46
Setting up Databases on Your Server	47

Introduction

Unlike normal hosting plans, which put many customers' accounts on a single server, a server is reserved exclusively for the account and use of a single customer. This means that you have exclusive rights to the server's bandwidth, memory, and storage space.

When you purchase a server, you actually lease a server box that remains at our data centers, which you can configure and set up according to your preferences.

Assisted Service Plan is a server option that shifts the responsibility of setup, monitoring, maintenance, security, and patching of your server to our server support team.

Assisted Service Plan servers do not have root/system-level access, but we allow control over all other aspects of the server. The Parallels Plesk Panel is installed for advanced server management tasks.

SECURITY INFORMATION

Compared to shared hosting, a server offers more power and more versatility. You can run and install virtually anything on your server. However, with this added control comes added responsibility.

You are responsible for the security, backup, and maintenance of your server, unless you have purchased an Assisted Service Plan and/or Managed Backup Services.

CAUTION! Remember to keep your administrative password secure. Anyone who has administrative access to your server can manipulate the software and content that runs on your server.

Unless you have Managed Backup Services with your server, we do not automatically back up your server. We do, however, offer an FTP backup service with our servers. For more information about our FTP backup service, please visit our website.

You can also purchase a hardware firewall for your server from us. You can use a hardware firewall to control the traffic to and from your server. For more information about our firewall service, please visit our website.

REPROVISIONING YOUR SERVER

If, at any time, you want to revert to a clean setup on your server, you can reprovision it. Reprovisioning erases all of the content on your server's hard drive. Your server resets to its state at the time you first purchased it.

You can reprovision your server by using the Hosting Control Center.

To Reprovision Your Server

- 1. Log in to your Account Manager.
- 2. Click Servers.
- 3. Next to the account you want to use, click **Launch**.
- 4. Under the **Support** section, click **Reprovision Server**. The Reprovision Server page displays.
- 5. If you want to, enter a new **host name** and **user name**. These values default to the current host name and user name for the account.
- 6. Enter and confirm a new password, and then click Continue.

You receive a confirmation notice once your server is reprovisioned and ready to go. Typically, this takes less than five hours.

GETTING HELP

After you set up your server, you can easily get help by submitting a trouble ticket or initiating a chat session in the Hosting Control Center. Alternatively, you may contact Customer Support directly.

To Open a Trouble Ticket 1. Log in to your Account Manager. 2. Click Servers. 3. Next to the account you want to use, click **Launch**. 4. In the Hosting Control Center, under **Support**, click **Trouble Tickets**. 5. Enter your **contact information**, including an email address and phone number. 6. Under Trouble Ticket Description, enter a summary and a detailed description of your issue. 7. Click Continue. 8. Review your trouble ticket information and click **Submit**. To Open a Chat Session 1. Log in to your Account Manager. 2. Click Servers. 3. Next to the account you want to use, click Launch.

4. In the Hosting Control Center, (in the top-right corner of the window) click Chat Now!

OTHER RESOURCES

Use these resources to learn more about managing your server:

Parallels Plesk Panel Manuals	http://www.parallels.com/products/plesk/resources/
	You can find user manuals and Flash tutorials on Parallels' website.
CentOS Documentation	http://www.centos.org
	You can find User Manuals on CentOS' website.

Setting up Your Server

Once you have purchased your server and we've worked on the initial configuration, you need to log in to your Hosting Control Center to finish setting things up.

The Hosting Control Center is an easy place for you to set up your server's host name, user name, and password. You can also use it to schedule server maintenance, reprovision your server, view bandwidth stats, request additional IPs, and submit trouble tickets.

CHOOSING A HOST NAME, USER NAME, AND PASSWORD

Servers with Assisted Service Plan require you to supply additional information, including the domain name you're using for your website's hosting or the email address for receiving server correspondence.

When setting up your server, you create a host name, user name, and password for your server. This is the user name and password that you will use to connect to your server in the future. It's a good idea to have this material ready when you log in for the first time.

Choosing a Host Name

The server's host name (also known as your account name) is a unique name for your server. If you have multiple servers, the host names help you differentiate among them.

A host name can be anything, as long as it:

- Contains 3–15 characters
- · Starts with a letter
- Only includes letters, numbers, periods, or a hyphen
- **Does not** start or end with a period or hyphen
- Does not include any spaces or any other special characters

Choosing a User Name

A user name is the primary ID that you use to access your server. This is also the user name you use to access your server from an SSH or SCP program.

CAUTION! Due to security reasons, you cannot log in directly to your server as root. However, you do have root access if you did not purchase Assisted Service Plan. To gain root access to your server, log in with your usual user name and then use the su – command.

To learn more about root access, see Gaining Root Access on Your Servers.

Your user name can be between 4 and 32 lowercase alphanumeric characters. Your user name cannot:

• Begin with a number

• Contain spaces, symbols, or capital letters

You **cannot** use the following reserved terms as a user name:

adm	binftp	halt	nobody	rpc	system
admin	body	iusrlp	nscdntp	rpcuserrpm	uucp
administrator	games	mailnull	operator	smmsp	vcsa
anonymous	gopher	news	рсар	sshd	
backup	guest	nfsno	root	sync	

Choosing a Password for Your Server

Your server's password, along with your user name, is used to connect to or gain root access to your server. Keep in mind that Assisted Service Plan servers do not allow root access.

To ensure your server is kept secure, your password must:

- Contain 7–14 characters
- Include lowercase letters, uppercase letters, and numbers
- Not begin with a number or symbol
- **Not** contain backslashes, colons, single quotes, double quotes, spaces, ampersands (&), or the caret symbol (^)
- Not contain your user name

LOGGING IN TO YOUR MANAGER FOR THE FIRST TIME

Once you've selected a host name, user name, and password for your server, you can log in to your Hosting Control Center and finish setting it up.

To Finish Setting up Your Server

- 1. Log in to your Account Manager.
- Click Servers.
- 3. Next to the server you want to use, click **Launch**.
- 4. On the Account Setup page, enter the **host name** for your server.



- 5. Enter your **user name** and **password** for your account.
- 6. Click Continue.
- 7. Confirm your settings and click Submit.

Once you click Submit, your server should be ready to use in approximately 12 hours. You receive an email message once it is ready.

Connecting to Your Server

In general, there are two different ways you can connect to your server. You can use a Webbased interface like Plesk, or you can connect directly to your server using the Secure Shell protocol (SSH).

Either way, you connect to your server using your server's IP address, the user name, and the password you specified when you set up your account. If you are connecting to your account using Plesk, log in with the user name "admin" instead of the user name you specified when you set up your account.

NOTE: If you have the Assisted Service Plan you will log in to Plesk with the user name that you picked during setup.

To find the IP addresses for your account, log in to your Hosting Manager. It lists the IP address for your server on the first page you see after you log in.

Depending on how you configured your server, you may have multiple IP addresses to choose from. You can use any of your IP addresses to connect to your server.

CONNECTING TO YOUR SERVER USING PLESK

Plesk is a Web-based control panel that you can use to manage your server. More specifically, you can use Plesk to set up your domain, DNS, and email on your server.

Make sure you have your IP address ready before you try to log in to Plesk. You'll need to use your IP address to access Plesk on your server. You can find the IP address to your server in your Hosting Manager.

This procedure explains how to log in to Plesk for the first time and includes some post-installation steps. You only need to perform these steps once.

NOTE: Not all Plesk options are available on servers with Assisted Service Plan. Assisted Service Plan server screenshots may differ slightly from those shown below.

To Access Your Server Using Plesk

1. Open a Web browser and go to:

https://[[ipaddress]]:8443/

Where [[ipaddress]] is your server's IP address.

- 2. When the Plesk login screen displays, enter admin as your user name (or the user name that you selected if you have the Assisted Service Plan). Enter the password you defined when you set up your server.
- 3. Read through and accept the SWsoft End-User License Agreement.
- 4. The post-installation configuration page displays. In the Full hostname field you can leave the default hostname that Plesk created for you, or you can enter your own fully qualified domain name. For example, host.coolexample.com.

Parallels

- 5. You can keep the default settings for the Select shared IP addresses. Plesk automatically fills in these fields based on your server and account information.
- 6. Under the **Shared IP addresses** section, select the primary IP address for your server in the list of **Exclusive IP** addresses, and click **Shared** >>. If you do not plan to host multiple domains on your server, you can skip this step.
- 7. Enter a password to use with the Plesk admin user. You can use the same password that you used to log in initially or create something new.

Username
Password

Interface language Default


Forgot your password?

Log in

Parallels* © 1999-2010, Parallels. All rights reserved.

8. Click **OK** to finish the post-installation configuration and log in to Plesk.

This is what the administrator interface looks like when you log in to Plesk for the first time:



The Server Administration screen in Plesk is the main dashboard that you use to manage and monitor your server. From here you can create new domains and email accounts, manage IP addresses, and start and stop services on your server.

Plesk has numerous features that can help you manage your server. To find out more about Plesk and the other features that we do not cover in this guide, please visit the SWsoft website at: http://www.swsoft.com/en/plesk/

For information about how to set up a domain and email using Plesk, see Adding a Domain to Your Server Using Plesk and Setting up Email on Your Server.

CONNECTING TO YOUR SERVER USING SSH

NOTE: This section is not applicable to Assisted Service Plan servers.

If you are a more experienced user and are comfortable using a command-line interface, you can use the Secure Shell, or SSH, protocol to connect to your server. First, download and install an SSH client on your computer. If you're using Windows, we recommend using PuTTY (http://www.putty.nl). Mac users can use Mac SSH (http://www.macssh.com). Linux and UNIX users can use OpenSSH.

Once you have installed an SSH client, log in to your server using your IP address, user name, and password. In this example, we use PuTTY.

Remember, before you log in to your server, make sure you have your IP address ready. You'll need to use your IP address to access your server. You can find the IP address to your server in your Hosting Manager.

To Connect To Your Server Using SSH (PuTTY) RuTTY Configuration Category: 1. Open your SSH client (PuTTY). - Session Basic options for your PuTTY session Specify the destination you want to connect to ⊤ Terminal Host Name (or IP address) Keyboard 2. In the Host Name (or IP Address) field, enter 62.74.125.122 Bell Features Connection type: the IP address for your server. C Raw C Telnet C Rlogin © SSH C Serial . Window :Appearance Load, save or delete a stored session: Behaviour 3. Click Open. This is the basic SSH command-Saved Sessions Translation Selection line interface. Colours Default Settings Load . Connection Data Save 4. Log in to your server with the user name and Proxy Delete Telnet password you created when you set up your Rlogin ± SSH account. Serial Close window on exit: ○ Always · ○ Never · ○ Only on clean exit 5. Once you log in, you can execute shell (Bash) About Cancel Open commands to navigate and manage your server.

Typically, only advanced users that are familiar with Linux and shell commands connect to their servers using SSH. You should be able to take care of most of your server management tasks using Plesk.

NOTE: This section is not applicable to Assisted Service Plan servers. On our dedicated and Virtual Private Linux servers, root is the administrative user that you can use to access and edit all of the files on your server (this includes system-critical files). You can also use root to install and uninstall programs on your server. Using root on your server can be dangerous. When you work on your server as root, you could potentially destroy important files and delete programs by accident. Typically, you should only use root to make one or two changes to your system and

You cannot log in to your server remotely using root. If you need root access on your server, use the \mathbf{su} - command once you have logged in with your user name.

The su (short for substitute user) command makes it possible to become the root user, temporarily, while you are logged in with your normal user name.

then switch back to your normal user account.

To use su to log in as root, type:

su -

By default, your root password is the same as the password you use with your normal user name.

When you are finished performing tasks as the root user, type exit to return to your normal user name.

To keep you data and server settings secure, only use root when necessary. Complete the task at hand, then **exit**.

Adding Domain Names to Your Server

As you probably already know, a domain name works a lot like an address forwarding service.

All of your website content sits on a computer with a unique address, your IP address. This is the same IP address that you use to connect to your server using Plesk. Your domain name directs visitors to your site using this IP address.

Before you set up a domain to host on your server, make sure you have already registered that domain through an accredited domain registrar.

To make the connection between domain name and IP address work, you need to first set up a domain and hosting on your server using Plesk. This section of the guide walks you through the necessary steps:

- **Step 1** Creating a Subscription in Plesk
- Step 2 Setting up Hosting for Your Domain

LOGGING IN TO PLESK

There are two ways that you can access the Plesk control panel on your server. You can log in to your Hosting Manager and click the Launch Plesk icon, or you can go to the following URL:

https://[[ipaddress]]:8443/

Where [[ipaddress]] is the IP address for your server.

STEP 1 - CREATING A SUBSCRIPTION IN PLESK

Before you add a domain to your server, you need to create a subscription in Plesk. All domains in Plesk have to be associated with a subscription.


You can use one subscription to set up multiple domains on your server or each domain can have a unique subscription.

To Create a Subscription in Plesk


1. Log in to Plesk using **admin** as your user name (or the user name that you selected if you have the Assisted Service Plan). Enter the password you defined when you set up your server.

If this is the first time you have logged in to Plesk, you'll need to read through and agree to the SWsoft End-User License Agreement and set up a new admin password for Plesk. See **Connecting to Your Server** on page 15 for more information.

2. From the menu on the left, select **Subscriptions**.



3. Click Add New Subscription.



4. To create a new subscription, enter the domain name, user name, password, and repeat password. The other fields on this page are optional.

This is where you create a ser	vice subscription for your own needs, as opposed to those made up to pro
Website Information —	
Properties of the website prov	risioned together with the subscription.
Domain name *	www.
IP address	62.74.125.122 (exclusive)
	IP address on which the website is hosted is a network address
Username *	
	System user account used to manage files and folders of the w
Password *	Very weak (?)

5. Click OK.

STEP 2 - CONFIGURING HOSTING SETTINGS FOR YOUR DOMAIN

Using the hosting configuration section of Plesk, you can determine what features you want to enable on your hosting account. For example: SSL, disk space, SSH access, FrontPage extensions, SSI, PHP, CGI, and Web statistics.

You can also decide if you want to physically host your domain on this server or forward it to another domain.

In the following example, we set up a basic, physical hosting account for the domain we created in **Step 1 – Creating a Subscription in Parallels Plesk Panel**. For more information about the various hosting features in Plesk, you can take a look at the Plesk documentation on SWsoft's website:

http://www.parallels.com/products/plesk/docs/

To Configure Hosting Settings for Your Domain in Plesk

- 1. If you're not already logged in to Plesk, log in using admin as your user name (or the user name that you selected if you have the Assisted Service Plan). Enter the password you defined when you set up your server.
- 2. From the menu on the left, select **Domains**.




3. From your list of domains, click Control Panel to the right of the domain you want to configure hosting settings for.


In this example, we set up hosting for coolexample.com.



4. This is the management page for your domain in Parallels Plesk Panel. In the **Domains list**, click the domain name you added.



- 5. This is the hosting settings page for your domain. Here, you have a number of hosting options for your domain. Go through the list and select the features you want to enable for this domain.
- 6. When you've finished selecting the features for your domain, click **OK**.



You can now access the directory for your domain and upload files using Plesk. However, for people to see your website online, you need to configure the DNS for your site.

The next section of this guide, Setting up DNS for Domains on Your Server, walks you through DNS setup. Once you configure the DNS for your site, you can FTP into your website hosting directory in the same way that you would with a traditional hosting account.

Plesk has numerous features that can help you manage your server. To find out more about Plesk and the other features that we do not cover in this guide, please visit the SWsoft website at:

http://www.parallels.com/products/plesk

Setting up DNS for Your Domains

Name servers are the Internet's equivalent to a phone book. A name server maintains a directory of domain names that match certain IP addresses.

This makes it possible for people across the Internet to access your website using a familiar domain name, instead of having to remember a series of numbers.

This section of the guide walks you through setting up your server as the name server for your domain and covers the procedure for assigning this name server to your domain.

After you set up your DNS, it can take up to 48 hours before your domain resolves to your IP address. This period is referred to as the propagation period.

We do not directly control the propagation period for your domain. While it should take no more than 48 hours, we cannot guarantee this time frame.

This section of the guide walks you through the necessary steps:

- Step 1 Creating a Zone File for Your Domain Name
- Step 2 Correcting the Nameserver Records in the Zone File
- Step 3 Creating and Registering Your Domain Hosts
- Step 4 Assigning the Nameservers to Your Domain

STEP 1 - CREATING A ZONE FILE FOR YOUR DOMAIN

To use your server as a name server, all of the domains on your server must have a zone file. A zone file is the file that maps your IP address to your domain name. It's easy to set up a zone file for your domain in Plesk, because Plesk automatically creates a zone file for any domain you set up.

If you have not set up your domain in Plesk, please see Adding a Subscription to Your Server Using Plesk before proceeding.

STEP 2 - CORRECTING THE NAMESERVER RECORDS IN THE ZONE FILE

Although Plesk creates a zone file by default it will only configure the NS and A records for **ns.** *yourdomain.com* (where *yourdomain.com* is your domain name). To ensure that your domain resolves properly you will need to alter the **ns.** *yourdomain.com* records as well as add an additional set of records to match the domain hosts you will create in **Step 3 - Creating and Registering Your Domain Hosts**.

To Register Your Domain Hosts in Parallels Plesk Panel

1. If you're not already logged in to Plesk, log in using **admin** as your user name (or the user name that you selected if you have the Assisted Service Plan). Enter the password you defined when you set up your server.





3. From your list of domains, click **Control Panel** to the right of the domain you want to configure the domain hosts for.



4. This is the management page for your domain in Plesk. In the **Websites and Domains section**, click **DNS Settings**.



5. Select the following entries, and then click Remove:

coolexample.com NS ns.coolexample.com
ns.coolexample.com A 62.74.125.122

- 6. Select Confirm removal, and then click OK.
- 7. Click Add Record, complete the following fields, and then click OK:

Record Type	Select A.
Domain Name	Enter the first domain host you want to use. We recommend NS1, but you can enter anything.
IP address	Enter your server's IP address.

8. Click Add Record again, complete the following fields, and then click OK:

Record Type	Select A.
Domain Name	Enter the second domain host you want to use. We recommend NS2, but you can enter anything.
IP address	Enter your server's IP address.

9. Click Add Record again, complete the following fields, and then click OK:

Record Type	Select NS .
Domain Name	Leave this field empty.
IP address	Enter your first domain name host, followed by a dot, and then the domain name you are using. For example, <i>ns1.coolexample.com</i> .

10. Click Add Record again, complete the following fields, and then click OK:

Record Type	Select NS.
Domain Name	Leave this field empty.
IP address	Enter your second domain name host, followed by a dot, and then the domain name you are using. For example, ns2.coolexample.com.

STEP 3 - CREATING AND REGISTERING YOUR DOMAIN HOSTS


Once you set up a domain and create a zone file in Plesk, you need to create and register two domain hosts for your domain at the registry. If your domain is registered with us, you can log in to your account manager to complete this step.

If your domain name is registered with another company, you need to contact them for instructions regarding domain host registration.

To Register Your Domain Hosts

- 1. Log in to your Account Manager.
- 2. From the **Domains** section, select **Domain Manager**.
- 3. Click the domain name you want to host on your server.

4. On the bottom-left of the page, next to Host Summary, click (add).



5. Complete the following fields, and then click **OK**:

Host name	Enter the first host name you created. For example, <i>ns1</i> .
Host IP 1	Enter your server's IP address

6. Click (add) again, complete the following fields, and then click OK:

Host name	Enter the second host name you created. For example, ns2.
Host IP 1	Enter your server's IP address

These domain hosts can be used for other domains hosted on your server. You do not need to create new domain hosts for each of your domains.

STEP 4 – ASSIGNING THE NAME SERVERS TO YOUR DOMAIN

Now that you created and registered two domain hosts, you need to change the information for your domain to use these new servers. If your domain is registered with us, you can log in to your account manager to complete this step.


If your domain name is registered with another company or you manage the DNS for your domains with a third-party tool, you'll need to contact them for information about assigning name servers to your domain.

To Assign the Name Servers to Your Domain


- 1. Log in to your Account Manager.
- 2. From the **Domains** section, select **Domain Manager**.
- 3. Click the domain name you want to host on your server.
- 4. From the Name Servers section, click Set Nameservers.



5. Select I have specific nameservers for my domains.



6. In the **Nameserver 1 and Nameserver 2** fields, enter the names of the domain hosts you created previously. For example, *ns1.coolexample.com* and *ns2.coolexample.com*.



7. Click **OK**.

ACCESSING YOUR DOMAIN USING FTP (UPLOADING FILES)

After you set up your DNS, it can take up to 48 hours before your domain resolves to your IP address. This period is referred to as the propagation period.

Once your domain resolves, you will see the default Parallels Plesk Panel index page when you

domain name into a browser. This is an example of the default Parallels Plesk Panel index page.

type your

When this page displays, you can connect to the hosting account for your



domain using FTP or through Parallels Plesk Panel to upload files to your website.

To make your Web pages viewable, upload them to the "httpdocs" directory in your hosting account. This directory is the root directory for your website.

Setting up Email on Your Server

Once you have set up your domain and hosting, setting up email accounts in Plesk only takes a few steps.


If you followed the procedure in the previous section of this guide to set up the DNS for your domain, you do not need to modify your MX records to set up email accounts in Plesk.

USING PARALLELS PLESK PANEL TO SET UP AN EMAIL ACCOUNT

The easiest way to set up an email account for a domain on your server is using Parallels Plesk Panel.


To Set Up Email Accounts for Your Domain in Plesk

1. If you're not already logged in to Plesk, log in using **admin** as your user name (or the user name that you selected if you have the Assisted Service Plan). Enter the password you defined when you set up your server.





3. From your list of domains, click **Control Panel** to the right of the domain you want to use.







5. Complete the following fields, and then click **OK**:

E-mail address	Enter the email address you want to create at the domain name.
Mailbox	Select Mailbox , and then select the size of the mailbox.
Password & Confirm Password	Enter the password for the email account.

ACCESSING YOUR ACCOUNT WITH AN EMAIL CLIENT

To access your email account using an email client, such as Outlook, Thunderbird, or Entourage, you need this information:

User Name	The name of the email account you created in Parallels Plesk Panel, for example: admin@coolexample.com.
Password	The password you specified in Parallels Plesk Panel when you set up your email account.
POP3	mail.coolexample.com (coolexample.com is your domain name).
SMTP Setting	mail.coolexample.com (coolexample.com is your domain name). The outgoing (SMTP) server requires authentication and uses the same user name and password as the incoming (POP3) server.

For more information about setting up mail accounts in Parallels Plesk Panel, you can look at the Parallels Plesk Panel documentation on Parallels' website.

USING WEBMAIL TO ACCESS YOUR EMAIL

Instead of accessing your email using a traditional email client, you can access your email on the Web using a standard Web browser.

If you have Webmail enabled in Parallels Plesk Panel, you can access your email at:

http://webmail.coolexample.com (coolexample.com is your domain name).

Log in to your account using the user name and password you set up in Parallels Plesk Panel or provided to you by your administrator.

Setting up Databases on Your Server


Many websites will need to use databases in order to function properly. Plesk lets you create databases and database users in your server's control panel.

To Create a MySQL Database in Plesk


- 1. If you're not already logged in to Plesk, log in using **admin** as your user name (or the user name that you selected if you have the Assisted Service Plan). Enter the password you defined when you set up your server.
- 2. From the menu on the left, select **Domains**.




3. From your list of domains, click Control Panel to the right of the domain you want to use.



4. From the the Websites & Domains section, click Show Advanced Operations.



5. Click Databases.





Install an SSL certificate on a domain to secure data that your site visitors send to and receive from the site.

Backup Manager

Back up and restore your domains, including settings and content of websites and mail accounts.



Restrict access to selected areas of your websites with password protection.



View logs and configure recycling of log files.



Web Users

View the list of users having personal web pages on your websites, and manage their accounts. Web users are limited user accounts that cannot log in to the Panel; they can only access a directory under one of your sites and host their sites there.



View and manage scheduled tasks.



Bandwidth Limiting

Adjust the limit on bandwidth usage and connections to your websites.




Install and manage Java applications.

Databases

Create and remove databases used by your websites, and manage them using integrated administrative web application.

Domain Aliases

View and manage alternative domain names for your websites.




6. Click Add New Database.

7. Enter a **Database name**, and then click **OK**. The other fields on this page are optional.

To Create a MySQL Database User in Plesk

1. If you're not already logged in to Plesk, log in using **admin** as your user name (or the user name that you selected if you have the Assisted Service Plan). Enter the password you defined when you set up server.







3. From your list of domains, click **Control Panel** to the right of the domain you want to configure a database for.



4. This is the management page for your domain in Plesk. Under **Websites and Domains**, click **Show Advanced Operations**.



5. Click Databases.



accounts. Web users are limited user accounts that cannot log in to the Panel; they can only access a directory under one of your sites and host their sites there.



Backup Manager

Back up and restore your domains, including settings and content of websites and mail accounts.



View and manage scheduled tasks.

Databases

Create and remove databases used by your websites, and manage them using integrated administrative web application.

Adjust the limit on bandwidth usage and connections to your websites.


Domain Aliases

View and manage alternative domain names for your websites.


Java Applications

Install and manage Java applications.

6. Click the name of the database that you want to use.



7. Click Add New Database User.



- 8. Enter a Database user name, New password, and Confirm password.
- 9. Click OK.